

# **RAD-Series AAA Server Getting Started Guide**

Version 7.4 for Solaris

---

© 2004-2008 Interlink Networks, LLC. All Rights Reserved.

This document is copyrighted by Interlink Networks, LLC. (Interlink Networks). The information contained within this document is subject to change without notice. Interlink Networks does not guarantee the accuracy of the information.

### Trademark Information

Brand or product names may be registered trademarks of their respective owners.

### Revision History

Date	Version	Type
10/2006	7.2.0	New Product Release
12/2007	7.3.0	New Product Release
07/2008	7.4.0	New Product Release

Interlink Networks, LLC.  
2500 Packard Street, Suite 202  
Ann Arbor, MI 48104

Main - (734) 821-1200  
Sales - (734) 821-1228  
Fax - (734) 821-1235  
Website - [www.interlinknetworks.com](http://www.interlinknetworks.com)

---

# Table of Contents

.....	i
<b>Table of Contents</b> .....	<b>i</b>
<b>About this Document</b> .....	<b>1</b>
Audience .....	1
Notational Conventions .....	1
<b>Preparation</b> .....	<b>2</b>
System Requirements .....	2
Compatibility .....	2
Java Run-Time Environment .....	3
Upgrading .....	3
Customizations .....	3
Before Installing over an existing installation .....	3
After Installing .....	4
Certificates .....	4
<b>Installation</b> .....	<b>5</b>
Installation Process .....	5
Installing RAD-Series Software .....	6
Installation Directories .....	8
Uninstalling RAD-Series Software .....	9
Starting Server Manager .....	9
Changing the Server Manager Port .....	10
Stopping Server Manager .....	10
Starting Remote Control .....	10
Accessing Server Manager .....	10
Adding Servers to Server Manager .....	11
Starting the Server .....	11
Testing Server Installation .....	12
<b>Configuration</b> .....	<b>13</b>
Configuration Process .....	13
Using Server Manager .....	13

Basic Server Configuration . . . . .	15
Load Configurations . . . . .	15
Define Access Devices . . . . .	15
Define Local Realms . . . . .	16
Save Configurations . . . . .	17
Restarting the Server . . . . .	17
Securing the Server . . . . .	17
<b>Basic Server Administration . . . . .</b>	<b>19</b>
<b>Licensing . . . . .</b>	<b>20</b>
Ordering a License . . . . .	20
Installing the License . . . . .	20
<b>Technical Support . . . . .</b>	<b>21</b>
Web Site . . . . .	21
Help Desk . . . . .	21

# About this Document

Welcome to RAD-Series AAA Server software. This guide will help you get started with:

- Installing the software
- Basic server configuration for a wired or wireless network
- Basic server administration

Consult the RAD-Series *Administrator's Guide* for advanced configuration and administration instructions.

## Audience

This *Getting Started Guide* is for Network and Systems Administrators who must install and configure the AAA Server. It's assumed that you:

- Are familiar with basic Unix commands
- Have full installation privileges on the machines where you will install the software
- Know the hardware and software profiles of the server machines and other devices used throughout the network
- Know how you will store user profiles for those accessing the network
- For wireless, know the EAP methods and user name formats used

## Notational Conventions

Text in this guide is marked in different styles to denote various things.

Text Marked...	Indicates...
<code>Fixed-width font</code>	This is code, a command, a file name, or a file parameter. Enter exactly what is shown.
<i>Fixed-width italic</i>	This is a variable. Enter what is correct for your installation, not what is shown.
<i>Normal italic</i>	This is the title of a book or other publication.
<b>Bold</b>	This is something noteworthy, so we emphasize it.
<a href="#">Blue underline</a>	This is a hypertext link. Click the link to send e-mail to the account, or to open the document in your browser.

## Preparation

Before installing the software:

- Be sure the host machine meets minimum system requirements
- Bring all software up to required patch levels
- If upgrading, read the section on Upgrading below and decide how you will handle previously installed components

## System Requirements

Each licensed copy of the AAA Server can be installed on one machine. The machine where the server is installed must have:

Specification	Requirement
Operating System/Platform	Sun Solaris 8, 9 or 10 on UltraSPARC hardware
Memory	64 MB RAM minimum 128 MB RAM or higher recommended
Disk Space	82 MB for server and Server Manager 100 MB temporary space for installer Additional disk space will be required depending on the amount of local logging.
Browser	Mozilla 1.6 Microsoft Internet Explorer 5.5 or higher The browser preferences / Internet options should be set to always compare loaded pages to cached pages.
Other	Java Run-time Environment (JRE) version 1.3.x or 1.4.x on each administrator workstation accessing Server Manager.

## Compatibility

See the publication [Supported and Interoperable Devices and Software Tables for RAD-Series Server](#) for a list of compatible hardware and software.

## Java Run-Time Environment

The Server Manager can be accessed from any workstation with a browser and the Java Run-Time Environment (JRE) installed. The JRE is required to run applets that are part of the Server Manager graphical user interface. Download and install the JRE on each machine you will use as an administrator workstation. You can download the JRE from:

[/http://www.java.com/downloads/](http://www.java.com/downloads/)

## Upgrading

Version 7.4.0 of the AAA Server software converts most previously installed binary and configuration files to version 7.4.0 formats during the installation process. You no longer need to uninstall the software prior to upgrading. To take advantage of this feature, you must install all files into the same directories as your previous installation. For safety's sake you may want to copy your current install to new directories and install/upgrade the copies. Then when you have finished testing the new version, stop the radius server and server manager and copy all **but** the log directory to the permanent directories and restart the server.

---

**Note:** When converting, you don't have to perform a preliminary backup of configurations. The AAA Server installer automatically backs up your current configuration files to the subdirectory `backup_raddb.timestamp` in the configuration file directory.

---

If you're converting from a version earlier than 6.0.x, check the conversion of your `vendors`, `dictionary`, and `.fsm` files. In some cases, these may need to be manually updated to include 7.4.0 content.

Finite State Machine (`.fsm`) files that have been modified from the installation default are not converted with the 7.4.0 installation. These files must be manually recreated in the 7.4.0 file format after installing the server.

## Customizations

If you created custom plug-ins for your AAA Server, you'll have to recompile them in version 7.4.0 of the Authentication-API (formerly SDK) to make them compatible with version 7.4.0 of the server.

## Before Installing over an existing installation

- 1 Stop the server, Remote Control, and Server Manager programs.
- 2 If you choose to uninstall rather than convert files:
  - Back up accounting and log files.
  - Back up configuration files.
  - Run `raduninstall` (in `/opt/aaa/uninstall` by default) to remove the original files.
  - Manually delete the remaining files.

## After Installing

- 1 If you have modified your state table (.fsm) files you will need to re-make your changes you made since your previous installation.
- 2 Restart the server, Remote Control, and Server Manager programs.

## Certificates

The AAA Server software is delivered with a certificate, key file, and self-signed certificate authority list that can be used for preliminary testing. However, if your application requires certificates, you should replace these with your own files before the server goes into production.

The following authentication methods require a server-side certificate:

- PEAP-MSCHAP
- PEAP-MD5
- PEAP-GTC
- TLS
- TTLS
- TTLS-MD5
- TTLS-PAP
- TTLS-CHAP
- TTLS-MSCHAP

# Installation

## Installation Process

The AAA Server installation process is:

- 1 Install software components on server machine(s).
- 2 Start the Server Manager program.
- 3 Start the Remote Control program on any machines where it is installed.
- 4 Access the Server Manager.
- 5 Add remote servers (if any) to Server Manager.
- 6 Start the server(s) from Server Manager.
- 7 Test installation using the preset configuration.

---

**Note:** This test can only be performed on the machine hosting the Server Manager program.

---

At the conclusion of this process, you'll:

- Know that the server software is installed and working properly
- Be ready to go on to basic server configuration

## Installing RAD-Series Software

To install the software:

1 Log on as root.

2 Run the installer:

```
# sh /download directory path/RAD-Series.7.4.0.solaris.sun4u.bin
```

---

**Note:** The installer will prompt you for each step of the process. To return to a previous step, enter `back` until you reach the form you need. To exit the installer, enter `quit`.

---

3 Enter the option number for each component to install on this machine, separated by commas (no spaces). For example:

```
ENTER A COMMA-SEPARATED LIST OF NUMBERS REPRESENTING THE COMPONENTS
TO BE INSTALLED: 1,2
```

Your options are:

Option	Component	Required
1	Server—the AAA Server programs, configuration files, libraries, plug-ins	On each host machine.
2	Server Manager—the browser-based interface for configuring and administering the server(s)	On a local server host machine. Only one installation is needed.
3	Remote Control—the RMI objects that facilitate communication between the Server Manager program and remote servers that host the AAA Server software	On each machine you will administer remotely. You do not need Server Manager on these machines.
4	Oracle server—the <code>db_srv</code> daemon that provides the interface between the Oracle database and AAA Server.	On the machine that hosts the Oracle database. If not the same as the AAA Server host, install this component later on the Oracle host.

4 Enter the installation directory for each file type. To accept the default directories, just press Enter at each prompt.

**If this is a fresh installation, then also:**

5 Enter a shared secret. This is a code used to establish a trust relationship between the AAA Server and its test utility. It cannot be more than 255 characters or contain spaces. The default is `secret`.

6 Enter a test user password. This password is used to test installation. The user password cannot have spaces or the backslash character. The default is `password`.

- 7** Enter a Server Manager user name. This is the name you'll use to log on to Server Manager. The default is `adminaaa`.
- 8** Enter a Server Manager password. This is the password you'll use to log on to Server Manager. The default is `adminaaa`.

## Installation Directories

As supplied, the RAD-Series software is installed into the following directories:

Directory	Contains
/opt/tomcat	Server Manager program
/opt/aaa/remotecomrol	RMI objects and startup script
/opt/aaa/lib	Libraries
/opt/aaa/bin	Server programs and utilities
/opt/aaa/uninstall	Uninstaller
/opt/aaa/aatv	Plug-ins
/opt/share/aaa/man	MAN pages
/opt/share/aaa/doc	PDF documentation
/etc/opt/aaa	Configuration files (including dictionary and vendors files)  *.fsm files: sample finite state machine (FSM) tables
/etc/opt/aaa/proldap	Schema files and sample LDIF files for LDAP authentication
/etc/opt/aaa/security	Certificates and keys for TLS, TTLS, and PEAP authentication
/etc/opt/aaa/fsm7.4	FSM, group, vendor and dictionary files for 7.4. They are copied to the configuration directory if this is a new install or the old files were not modified by you.

## Uninstalling RAD-Series Software

The RAD-Series software is delivered with an uninstall script, `raduninstall`, found in the `uninstall` subdirectory of the server directory (default `/opt/aaa/uninstall`).

- 1 Login and change directory to `/server directory/uninstall`.
- 2 Run `raduninstall`.
- 3 When prompted, press Enter.
- 4 Manually delete any files modified since installation.

---

**Note:** Modified files include files utilized and changed by the server in the course of normal operation, and their directories.

---

## Starting Server Manager

Server Manager is the browser-based application for configuring and managing all your AAA Servers. Once started, you can access Server Manager from any networked workstation that has a browser and a Java Run-Time Environment installed.

Server Manager can be set up to make a Secure Socket Layer (https) connection to administrator workstations. See “Configuring Server Manager for SSL” in the *RAD-Series Administrator’s Guide*. The steps below show how to start Server Manager using a non-secure (http) connection. We recommend doing this to complete the initial server set up.

On the machine where you’ve installed Server Manager:

- 1 Change directory to `/Server Manager directory/bin` (`/opt/tomcat/bin` by default).
- 2 Run `startup.sh`.

### If the process fails to start:

- 3 Check the log file `catalina.out` (in `/opt/tomcat/logs` by default).  
If you see the message “Root cause - Address already in use,” the default port 8080 is already being used by another process.
- 4 At your shell prompt, enter `lsof -i :8080` to identify the process currently using port 8080.
- 5 Either change the Server Manager port, or kill the process using the port.

## Changing the Server Manager Port

If you can't use the default port of 8080 for Server Manager:

- 1 In a text editor, open the file `server.xml` (in `/opt/tomcat/conf` by default).
- 2 Locate the following lines:

```
<Connector className="org.apache.coyote.tomcat4.CoyoteConnector"
    port="8080" minProcessors="5" maxProcessors="75"
    enableLookups="true" redirectPort="8443"
    acceptCount="100" debug="0" connectionTimeout="20000"
    useURIVValidationHack="false" disableUploadTimeout="true" />
```

- 3 Change "8080" to the port you wish to use.
- 4 Save and close `server.xml`.
- 5 Stop and restart Server Manager.

## Stopping Server Manager

To stop the Server Manager program:

- 1 Change directory to `/Server Manager directory/bin`.
- 2 Run `shutdown.sh`.

## Starting Remote Control

On each machine where you've installed Remote Control:

- 1 Change directory to `/Remote Control directory`.
- 2 Run `rmistart.sh`.

## Accessing Server Manager

Once the Server Manager program is started, to access the graphical user interface:

- 1 Open your browser and enter the URL `http://IP-address:Port/aaa` where:
  - `IP-address` is the IP for the machine that hosts the Server Manager program.
  - `Port` is the port number assigned to Server Manager. Default is 8080.
- 2 Enter the Server Manager administrator user name and password you choose at installation.

- 3 If this is the first time you're accessing Server Manager, enter the user name and password again to authenticate to the Java Run-Time Environment.

You'll see the Server Manager Administration page, with localhost listed in the Status frame. Bookmark this page in your browser for ease of access later on.

---

**Note:** If you see a Java run-time error in the Status frame, the workstation may not have the Java Run-Time Environment installed, or the second Java logon box may be hiding behind other windows awaiting your entry. See "Java Run-Time Environment" on page 3 for more information.

---

## Adding Servers to Server Manager


If you've installed AAA Servers and Remote Control objects on remote machines, add them to the list of servers managed by Server Manager.


- 1 Access the Server Manager.
- 2 In the Navigation tree on the left, click Managed Servers.
- 3 In the main area on the right, click the Connect to Server link.
- 4 Enter a Name for the server to appear in Server Manager. This doesn't have to be the actual server name, just an identifier.
- 5 Enter the server's IP address or fully-qualified domain name.
- 6 Click Create.

The server now appears in the Server Status area at the lower left of the screen.

## Starting the Server

- 1 Access the Server Manager.
- 2 In the Server Status area at the lower left of the screen, select the server by checking the box.
- 3 In the main area to the right, click Start.

If you see a green  icon next to the server name in the Status area, the server started.

If you see a red  icon, the server failed to start. See the Troubleshooting section of the Interlink Networks' Frequently Asked Questions page at [www.interlinknetworks.com/support/faq7-1.htm](http://www.interlinknetworks.com/support/faq7-1.htm) for possible solutions.

## Testing Server Installation

The AAA Server is delivered with a very simple wired network configuration designed to help you test that the server is installed and authenticating correctly (using password authentication). We recommend running this test before proceeding with server configuration.

1 Follow the procedure above to start the server in Server Manager.

2 With the server still selected, click the Status button in the main area.

If the server is operational, you'll see the message:

```
RADServer-name (RAD-port) is responding
```

3 Toggle to your shell account.

4 Set the library path (`/opt/aaa/lib` by default):

```
# export LD_LIBRARY_PATH=/server library path
```

5 Change directory to `/server binary path` (`/opt/aaa/bin` by default).

6 Run `radpwtst -s localhost test_user`.

7 When prompted, enter the test user password you specified during installation.

A message appears summarizing authentication. If the server is authenticating properly, the final line in the message is:

```
"test_user" authentication OK
```

8 To terminate the test process:

```
# kill pid
```

Where `pid` is the radius process ID. You can determine this by:

```
# ps -ef | grep radiusd
```

---

**Note:** Remove the `test_user` from the localhost configuration when you're done using the test tool. See the *RAD-Series Administrator's Guide* for instructions.

---

If you encounter problems while running the test, see the Troubleshooting section of the Interlink Networks' Frequently Asked Questions page at [www.interlinknetworks.com/support/faq7-1.htm](http://www.interlinknetworks.com/support/faq7-1.htm).

# Configuration

The topics in this section will help you begin to set up the server for your network. After completing them, see the RAD-Series *Administrator's Guide* to finish your server configuration.

## Configuration Process

The basic configuration process is:

- 1 Load existing configurations into Server Manager.
- 2 Define network access devices.
- 3 Define local realms, including:
  - Realm name
  - Authentication method
  - Users
- 4 Save configuration to server.
- 5 Restart the server to enable the new configuration.

By the end of this process, you'll have:

- At least one realm defined
- At least one user set up for authentication using your method

## Using Server Manager




We recommend using Server Manager, rather than command-line functions, to perform basic AAA Server configuration and administration.

Server Manager works by loading a duplicate of the current server configuration into a temporary workspace. After you've made your changes in the workspace, you save the new configuration to the server itself, then restart the server to enable the changes.

When you leave Server Manager between sessions, it automatically holds your configuration changes in the temporary workspace files. You do not need to save until you are ready to push the configuration to one or more servers.


The Server Manager interface contains four primary work areas:

The screenshot shows the RAD-Series Server Manager interface. On the left is a navigation frame with a tree view of menu items. The main area is divided into three sections: a status frame at the bottom left showing server status for 'localhost' with a green 'GO' icon; a workspace frame in the center titled 'Administration' containing a table of server commands (Start, Stop, Restart, Status, Time) with buttons and help icons; and a message frame at the bottom right showing a command log with a blue 'Result' box indicating 'Starting RAD-Series Server(s) on localhost Server successfully started.'

- 1 **Navigation frame**—In this area, you choose the tasks you want to perform on the selected servers. The Workspace frame changes according to your selection.
- 2 **Status frame**—This area shows the servers in your installation and their current on/off status.
  -  means the server is running
  -  means the server is stopped
  -  means there's been a server error or communication error

Any server commands you execute from the Administration page affect whatever servers are selected here.
- 3 **Workspace frame**—This area contains the controls for configuring and administering servers. It changes based on the task you've selected.
- 4 **Message frame**—This area shows the results of log file searches and server commands.

Each Workspace page contains both buttons and links you can use to drill-down to other forms. Hover over any button to see what it does. Required fields are marked with an asterisk (\*). To go back to the previous page in your work sequence, click the Cancel button at the bottom of the page or your browser's Back button.

Click the Field Help  buttons for definitions and acceptable values. For more detailed configuration instructions, use the Server Manager online Help, found in the Navigation frame.

## Basic Server Configuration

Before beginning server configuration, set up all your network devices, and list all shared secrets and device vendors. You'll need this information to complete the server configuration.

To start configuring the AAA Server, access Server Manager.

To quit configuration at any time, just close your browser.

### Load Configurations

Load the current server configurations into the Server Manager workspace. The initial download will contain the default wired configuration used to test the server installation.

- 1 In the Navigation frame, click Load Configurations.
- 2 In the Workspace frame, select the server to pull configurations from:
- 3 Click Load.


You'll be notified when the transfer is complete.

### Define Access Devices

Enter the IP address and a shared secret for each access point in your network.

You can enter any valid IP address (e.g.: 192.44.3.11) or fully-qualified DNS name (e.g.: nas.yourcompany.com).

The shared secret is the code that will be used to establish a trust relationship between the access device and the server. The shared secret can't exceed 255 characters or contain spaces.

- 1 In the Navigation frame, click Define Access Devices.
- 2 In the Workspace frame, click the New Access Device link or the Add  button.
- 3 In Name, enter the IP address or fully-qualified domain name.
- 4 Enter and confirm the Shared Secret.
- 5 The Vendor field specifies which set of vendor-specific attributes to return in RADIUS message sent to this device. Use CTRL + Click to select to select all that apply from the drop-down list. Choose Generic for none.
- 6 Click Create.

## Define Local Realms

If any of your users are required to enter a realm name to log in to the network (e.g.: @yourcompany.com), enter the:

- Realm name—any realm you’ve defined, or a fully-qualified DNS name, provided it’s what appears in the login string
- Authentication methods used by the realm
- User storage type
- User profiles, if using local storage

Enter as many realms as are needed.

If users do **not** have to enter a realm name to log in, modify the NULL realm and add users to it.

For each realm you’re defining:

- 1 In the Navigation frame, click the Local Realms link.  
You’ll see the NULL realm, set up Deny.
- 2 If users **do not** have to enter a realm name, click the NULL link.  
If users **do** have to enter a realm name, click the Add New Realm link and enter it in Name.
- 3 Choose the User Profile Storage type from the drop-down.  
New realms default to LDAP storage.
- 4 If this is a **wireless** network and additional parameters appear under Security Method:
  - Click EAP Authentication.
  - Choose all the EAP methods used by this realm. Use CTRL + Click to select more than one.


If this is a **wired** network, leave Password Authentication selected.

- 5 Add at least one user.

For an **LDAP server**:

- Under User Storage Parameters, choose New LDAP Directory from the drop-down.
- Enter the directory information and click Save.
- Click Create to save the realm definition.

For local storage:

- Click Create to save the realm definition.
- Click the View User List  button next to Local Storage for that realm.
- Click the New User link.
- Enter the required user information and click Create.

## Save Configurations

After you've completed the basic server configuration in Server Manager, save the configuration to the server.

If you're running several AAA Servers with the same configuration, you can select all the servers and push the new configuration to them at once.

- 1 In the Navigation frame, click Save Configuration.
- 2 In the Workspace frame, select the server(s).
- 3 Click Save.

## Restarting the Server

Server Manager includes a special restart function that enables you to apply most configurations without having to first stop the server. Some server properties and server startup options require you to stop the server. See the *Administrator's Guide*.

- 1 In the Navigation frame, click Administration.
- 2 In the Status frame, select the server.
- 3 In the Workspace frame, click Restart.

## Securing the Server

We recommend doing the following to make the server more secure, before putting it into production. Instructions for each of these procedures are in the RAD-Series *Administrator's Guide*.

- 1 Remove the `test_user` from the default `users` file if you plan to keep this file in your configuration.
- 2 Change the Server Manager user name and password from the installation default `adminaaa`.
- 3 Change the Server Manager shared secret (the secret Server Manager shares with each server it manages).
- 4 Configure the Server Manager to use SSL when communicating with workstations.
- 5 Change the Server Manager port number.

Following these guidelines will also improve server security:

- Don't install the AAA Server on user machines.
- Don't install the AAA Server on the same machine as other servers, like your web, FTP, and mail servers.
- Change the Current Directory of a server connection to a secure location to prevent public access to a core dump.

- Where possible, store hashed passwords in user profiles.

# Basic Server Administration

Basic administration for AAA Servers can be done using the Server Manager Administration page.

You can run any of these commands on several servers at once. Just select all the servers to be included from the Status frame.

- 1 Access the Server Manager.
- 2 Choose Administration from the Navigation frame.
- 3 In the Status frame, select the server(s) by checking the box.  
Be sure to **clear** the box for any selected servers where you don't want to run the command.
- 4 In the Workspace frame, click the command to perform:
  - **Start**—starts server operation after it's been stopped. You'll see a green GO icon next to the server name in the Status frame to indicate it's online.
  - **Stop**—stops server operation. You'll see a red STOP icon next to the server name in the Status frame to indicate it's offline.
  - **Restart**—let's you apply new configurations without having to first stop the server. First save the new configurations to push them to the server.
  - **Status**—checks whether the server is responding. If it is, you'll see the message `"Server-name (Port-number) is responding."`
  - **Time**—shows the date/time on remote servers.

# Licensing

The RAD-Series license enables a base set of features and limits the number of concurrent user sessions that the software maintains. The license may also enable and disable optional modules that extend the base feature set.

Initially, the software operates under an evaluation license with the full RAD-Series feature set. The evaluation license lasts 30 days, during which you can review the user documentation and other advanced features of the server.

After this time, you must purchase a license to retain the functionality. Be sure to purchase the appropriate license for your needs. If you've configured functions or users during evaluation that are not supported by the license you purchase, they will be disabled during production use.

Contact sales using our WEB site, [www.interlinknetworks.com](http://www.interlinknetworks.com), for more information about the different licensing options.

## Ordering a License

When you're ready to purchase a licensed version of the RAD-Series software, contact your sales representative at:

Phone: 734-821-1228

Fax: 734-821-1235

WEB site: [www.interlinknetworks.com](http://www.interlinknetworks.com)

## Installing the License

To install a license purchased for production use or to upgrade a feature set:

- 1 Backup any existing production licenses.
- 2 Copy the file `aaa.config.license` to your configuration directory (`/etc/opt/aaa` by default).
- 3 Access the Server Manager interface.
- 4 Restart the server in Server Manager.

# Technical Support

## Web Site

In addition to our printed product documentation, we offer free and unlimited support information on our web site. Visit the Frequently Asked Questions page at:

<http://www.interlinknetworks.com/support/faq7-1.htm>

You'll find a continuously updated list of solutions to common problems, instructions for advanced configuration tasks, and inter operability information.

## Help Desk

RAD-Series software is covered for a 30-day warranty period. During this time, you may contact our Help Desk for technical support at no additional charge.

To extend technical support beyond the 30-day warranty period, you can purchase a Software Maintenance Plan. Visit our WEB site to contact sales:

[www.interlinknetworks.com](http://www.interlinknetworks.com)

If you can't find the solution to your problem in our documentation or on the web site, and you're covered by a maintenance plan or the 30-day warranty, you can:

- E-mail [support@interlinknetworks.com](mailto:support@interlinknetworks.com)
- Phone 734-821-1222, Monday through Friday, 8:30 a.m. to 5:30 p.m. EST (except US holidays)

Be ready to provide the following information when you contact us:

- Version number of the AAA Server that you are using
- Operating system and its version
- Company name of licensee

Please don't e-mail any unsolicited log file or configuration file snippets longer than one hundred lines. We'll let you know if we need more information.